

# UPS OAuth2 For Magento



**Magento Compatibility Version 2.\***

## **Configuration Guide**

# UPS OAuth2 For Magento

## Table of Contents

Preface ..... 3

Introduction ..... 4

Configure Extension..... 4

Support. .... 7

# UPS OAuth2 For Magento

## Preface:

This document provides information on how to configure and use the **UPS OAuth 2** extension in Magento 2.

## Disclaimer:

Expound Coderz reserves the right to add, remove, modify, and add new features to this extension. Expound Coderz reserves the right to remove any feature of its products that does not fulfill expectations.

We don't give guarantees for our extensions worked on third-party Magento extensions or themes and custom work on default themes or extensions.

# UPS OAuth2 For Magento

## Introduction:

The extension **UPS OAuth 2** will integrate the UPS shipping with Magento 2 using the new Authorization Method OAuth 2.0 of UPS.

## How to configure.

### Configuration:

#### Step 1:

Log in to the Admin Magento. Navigate to **Stores > Configuration.**

Navigate to **Sales > Delivery Methods > UPS OAuth2.**

The screenshot displays the Magento Admin configuration page for the UPS OAuth2 extension. The left sidebar shows the navigation menu with 'Delivery Methods' expanded and 'UPS OAuth2' selected. The main content area shows the configuration settings for UPS OAuth2, including fields for 'Enabled for Checkout', 'Title', 'Mode', 'Client ID', 'Client Secret', 'Origin of the Shipment', 'Enable Negotiated Rates', 'Time in Transit', 'Show Estimate Time', and 'Use Dimensional'.

Field	Value	Use system value
Enabled for Checkout [website]	Yes	<input type="checkbox"/>
Title [store view]	United Parcel Service	<input checked="" type="checkbox"/>
Mode [website]	Live	<input checked="" type="checkbox"/>
Client ID [website]	[Redacted]	
Client Secret [website]	[Redacted]	
Origin of the Shipment [website]	Shipments Originating in United States	<input type="checkbox"/>
Enable Negotiated Rates [website]	No	<input checked="" type="checkbox"/>
Time in Transit [website]	No	<input checked="" type="checkbox"/>
Show Estimate Time [website]	No	<input checked="" type="checkbox"/>
Use Dimensional [website]	No	<input checked="" type="checkbox"/>

# UPS OAuth2 For Magento

## Step 2:

**Enabled for Checkout:** Set it to yes to enable the shipping methods.

**Title:** You can set the title or can use the default.

**Mode:** There are 2 modes

**Development:** The Customer Integration Environment allows customers to test their application prior to launch.

**Live:** Once testing is complete, direct your Rating Package to the production URL

**Client ID:** You can find the client ID in your UPS account application section.

**Client Secret:** You can find the client Secret in your UPS account application section.

**Origin of the Shipment:** The origin of the shipment is the reason UPS you are going to ship packages.

**Enable Negotiated Rates:** If you select "Yes" it will show negotiable Shipping rates to your customers.

**Show Estimate Time:** If you select "Yes" the estimated delivery time will show with every method.

**Use Dimensional:** If you select "Yes" it will show accurate dimensional shipping rates based on the dimensions you set for the products.

**Shipper Number:** Shipper Number is a UPS account number you are using for payment in your UPS account.

**Destination Type:** Destination type is used to change the rates and shipping methods, there are different methods for Commercial and Residential Destination with Different Rates.

**Allowed Methods:** You can choose the delivery method you want to show to your customers based on your "Origin of the Shipment".

NOTE: Most of the settings are the same as the default UPS extension of


# UPS OAuth2 For Magento

Magento 2.

## Step 3:

### Save Configuration:

After completing the configuration Click on the Save Config Button at the top right corner.



The screenshot shows a portion of the Magento configuration page. At the top right, there is an orange button labeled "Save Config". Below it, there are three configuration options, each with a checkbox labeled "Use system value". The first checkbox is unchecked, the second is checked, and the third is checked. To the left of each checkbox is a text input field with a dropdown arrow. At the bottom left, there is a small text label "mers to test their".

### Flush Cache:

Flush the Cache after saving the configuration and you are all set to use the UPS Shipping Method with your new API keys of OAuth 2.0.

# UPS OAuth2 For Magento

## Support:

You can contact us at:

**Email:** coderz.expert@gmail.com

**Support:** contact@expoundcoderz.com

We will be ready to help you always!

You can also send us your feedback. Comments, suggestions, and opinions are largely appreciated. You can also follow us on Facebook, Twitter, and LinkedIn to know the latest news and offers:

<https://www.facebook.com/expoundcoderz>

<https://twitter.com/contactexpound>

<https://www.instagram.com/expoundcoderz/>

<https://join.skype.com/invite/Y3wxY5koAZob>

<https://in.linkedin.com/company/expound-soft-tech-solution>